

# GitaGPT Humanoid Robot Setup Instructions

---

This guide will help you set up and run the GitaGPT system for Bhagavad Gita Q&A with robotic jaw movement. It is written for beginners and covers all essential steps, file locations, and configuration details.

---

## 1. System Overview

- **Server (Windows Laptop):**
    - Main file: `server_v6.py`
    - Handles AI, speech-to-text, verse search, and text-to-speech
  - **Client (Raspberry Pi):**
    - Main file: `client5.py`
    - Records audio, sends questions, plays answers, controls Arduino jaw
- 

## 2. Required Files & Where to Place Them

### On Windows (Server)

- **Example path shown below is for this guide only.**
- You must use your own Windows username and folder structure.
- To find your correct path:
  - Open File Explorer
  - Navigate to your Desktop or chosen folder
  - Copy the full path from the address bar
- Place these files in your chosen project folder, for example:  
`C:\Users\<YOUR_USERNAME>\OneDrive\Desktop\gitaGPT\`
  - `server_v6.py` (main server code)
  - `bhagavad_gita_verses.csv` (Gita verses data)
  - `gita_faiss.index` (auto-generated FAISS index)
  - `en_GB-southern_english_female-low.onnx` (Piper TTS voice model)

### On Raspberry Pi (Client)

- Place these files in your chosen Pi project folder, for example:  
`/home/pi/test/`
  - `client5.py` (main client code)

### Tip:

- You can use any folder you like, but you must update the file paths in your code to match where you put the files.
  - If you are unsure, ask for help or send a screenshot of your folder location.
-

### 3. How to Change File Paths in server\_v6.py

If your files are in different locations, you must update the following paths in `server_v6.py`:

- **FAISS Index Path:**

- Find the line:

```
FAISS_INDEX_PATH = os.environ.get("FAISS_INDEX_PATH",  
r"C:\Users\Raghuram S\OneDrive\Desktop\gitaGPT\gita_faiss.index")
```

- Change the path to where your `gita_faiss.index` file is located.

- **CSV Path:**

- Find the line:

```
DF_PATH = os.environ.get("DF_PATH", r"C:\Users\Raghuram  
S\OneDrive\Desktop\gitaGPT\bhagavad_gita_verses.csv")
```

- Change the path to where your `bhagavad_gita_verses.csv` file is located.

- **Piper TTS Voice Path:**

- Find the line:

```
PIPER_VOICE_PATH = os.environ.get("PIPER_VOICE_PATH",  
r"C:\Users\Raghuram S\OneDrive\Desktop\gitaGPT\en_GB-  
southern_english_female-low.onnx")
```

- Change the path to where your Piper `.onnx` voice file is located.

**Tip:**

- You can use absolute paths (full path from C:\ or /home/pi/) or relative paths (from your project folder).
- Always use double backslashes `\\` in Windows paths, or single slashes `/` in Linux paths.

---

### 4. IP Address and Port Configuration (Client)

- **Find your laptop's IP address:**

- On Windows, open Command Prompt and run: `ipconfig`
- Look for your WiFi IPv4 address (e.g., `192.168.104.80`)

#### 4. Update the Client Code: IP Address, Port, and Arduino Configuration

Before running the client, open your client Python file (e.g., `humanoid_gita_client.py` or `Client5.py`) and update the configuration section at the top to match your setup:

```
# Configuration
LAPTOP_IP = "192.168.104.80" # Your laptop IP
LAPTOP_PORT = 5000
SAMPLE_RATE = 16000
CHANNELS = 1
RECORD_SECONDS = 10

# Arduino configuration (from your original code)
ARDUINO_PORT = "/dev/ttyUSB0" # Change as needed
ARDUINO_BAUDRATE = 9600
```

- **LAPTOP\_IP:** Set to your Windows laptop's IP address (find with `ipconfig` on Windows).
- **LAPTOP\_PORT:** Should match the port number used by your server (default: 5000).
- **ARDUINO\_PORT:** Set to the correct serial port for your Arduino (use `ls /dev/tty*` on Raspberry Pi to find it).
- **ARDUINO\_BAUDRATE:** Usually 9600, but match your Arduino sketch if different.

If you get errors like "Connection refused" or "Serial port not found," double-check these settings and restart the client.

---

## 4a. Ollama Installation & Setup (Server)

Ollama is used for advanced AI text generation in `server_v6.py`. You must install and set up Ollama on your Windows laptop before starting the server.

Steps to Download and Install Ollama:

1. **Go to the Ollama website:**
  - <https://ollama.com/download>
2. **Download the Windows installer** and run it.
3. **Follow the installation instructions** to complete setup.

Steps to Set Up Ollama for GitaGPT:

1. **Open PowerShell and start the Ollama server:**

```
ollama serve
```

- This command must be running in the background while you use GitaGPT.

2. **Download the required model (e.g., Gemma):**

```
ollama pull gemma3:1b
```

- You can pull other models if needed. See <https://ollama.com/library> for options.

### 3. (Optional) Allow remote access:

- If you want to access Ollama from another device, set the environment variable before starting Ollama:

```
$env:OLLAMA_HOST="0.0.0.0:11434"  
ollama serve
```

- This allows connections from other devices on your network.

### 4. Check Ollama status:

- Visit <http://localhost:11434> in your browser to confirm Ollama is running.

#### Note:

- If you do not install or run Ollama, the server will use a fallback model (transformers), which may be slower or less accurate.
- For more help, see <https://ollama.com/docs/getting-started>

---

## 4. Virtual Environment Setup & Python Package Installation

### On Windows (Server)

1. Open PowerShell and navigate to your project folder:

```
cd "C:\Users\<YOUR_USERNAME>\OneDrive\Desktop\gitaGPT"
```

2. Create a virtual environment:

```
python -m venv gitagpt
```

3. Activate the virtual environment:

```
.\gitagpt\Scripts\Activate.ps1
```

4. Upgrade pip (recommended):

```
python.exe -m pip install --upgrade pip
```

5. Install all required Python packages:

```
pip install flask numpy openai-whisper sentence-transformers faiss-cpu
pandas scipy pyttsx3 piper-tts soundfile transformers comtypes pywin32
pyserial ollama
```

- Only **pyserial** is needed for serial communication; you do NOT need to install **serial** or **serial.tools** separately.

## On Raspberry Pi (Client)

1. Update and install Python3/pip:

```
sudo apt update
sudo apt install python3 python3-pip python3-venv
```

2. Create a virtual environment:

```
python3 -m venv gitaenv
```

3. Activate the virtual environment:

```
source gitaenv/bin/activate
```

4. Upgrade pip (recommended):

```
python3 -m pip install --upgrade pip
```

5. Install all required Python packages:

```
pip install sounddevice pyaudio pyserial requests
```

### Note:

- You only need to install these packages once per environment.
- If you see errors about missing modules, run the relevant pip install command above.

## 5. Customizing IP Address, Port, and Arduino Serial Port

After installing packages and before running the client, you must update the following settings in your client code (e.g., `humanoid_gita_client.py` or `Client5.py`) on your Raspberry Pi:

### How to Edit

1. Open your client Python file in a text editor (e.g., VS Code, nano, Thonny).
2. Find the section near the top that looks like this:

```
# Configuration
LAPTOP_IP = "192.168.104.80" # Your laptop IP
LAPTOP_PORT = 5000
SAMPLE_RATE = 16000
CHANNELS = 1
RECORD_SECONDS = 10

# Arduino configuration (from your original code)
ARDUINO_PORT = "/dev/ttyUSB0" # Change as needed
ARDUINO_BAUDRATE = 9600
```

### What to Change

- **LAPTOP\_IP:** Set this to your Windows laptop's IP address on the local network. Find it using `ipconfig` (Windows) or `ifconfig` (Linux/Raspberry Pi).
- **LAPTOP\_PORT:** Should match the port number used by your server (default: 5000).
- **ARDUINO\_PORT:** Set this to the correct serial port for your Arduino. Common values:
  - `/dev/ttyUSB0` (most USB Arduinos)
  - `/dev/ttyACM0` (some models)
  - Use `ls /dev/tty*` on Raspberry Pi to find the correct port.
- **ARDUINO\_BAUDRATE:** Usually 9600, but match your Arduino sketch if different.

### When and Why to Change

- Change these values **before running the client** for the first time, or whenever your network or hardware setup changes.
- If you get errors like "Connection refused" or "Serial port not found," double-check these settings.

### Troubleshooting

- If the client cannot connect to the server, verify `LAPTOP_IP` and `LAPTOP_PORT` match your server's actual IP and port.
- If you see errors about the Arduino port, run `ls /dev/tty*` on the Raspberry Pi to find the correct device name, then update `ARDUINO_PORT`.
- Restart the client after making changes.

---

## 6. Running the System

## On Server (Windows Laptop)

1. Activate your virtual environment:

```
.\gitagpt\Scripts\Activate.ps1
```

2. Start the server:

```
python server_v6.py
```

3. Wait for the "Server ready" message and ensure no errors.

## On Client (Raspberry Pi)

1. Activate your virtual environment:

```
source gitaenv/bin/activate
```

2. Run the client script:

```
python3 client5.py
```

3. The client will automatically:
  - Connect to the Arduino (if plugged in)
  - Handle audio recording and playback
  - Control the jaw movement
  - Communicate with the server
4. Follow on-screen instructions:
  - Press ENTER to record a question
  - Speak clearly for 10 seconds
  - Watch the jaw move during Gita's response

### Note:

- You do NOT need to manually connect to the Arduino or test TTS before running the client script. Everything is handled by the script.

---

## 7. Important Things to Change (Summary)

- **IP Address:**
  - Change the IP in the client code (`LAPTOP_IP` variable) to match your laptop's IP.

- **Server Port:**
    - Change the port in the client code (`SERVER_PORT` variable) if your server uses a different port.
  - **File Paths:**
    - Make sure all files are placed in the correct folders as shown above.
    - Update FAISS index, CSV, and Piper voice paths in `server_v6.py` if your files are in different locations (see section 9).
  - **Virtual Environment:**
    - Always activate the venv before running any Python scripts.
- 

## 8. Troubleshooting

- **Arduino Not Responding:**
    - Check USB connection and power
    - Try both `/dev/ttyUSB0` and `/dev/ttyUSB1` in your client code
    - Re-upload Arduino code if needed
  - **Audio Issues:**
    - Ensure microphone is connected to Pi
    - Test with `arecord` and `aplay` commands
  - **Virtual Environment Problems:**
    - Always activate the venv before running scripts
  - **General:**
    - If you see errors, check file paths, IP addresses, and package installations
- 

## 9. Summary

- Use **only** `server_v6.py` (server) and `client5.py` (client) for the final system.
  - Update IP addresses and file paths for your own setup.
  - Share this guide with anyone setting up the system—no prior experience required!
-